


Lecture 7: Basics of PDEs I

Note Title

1/10/2015

★ The Vibrating String: Vectorial Approach

We already derived a wave eqn. via Calc. of Var. Here, we shall try a more traditional vectorial approach to see that we reach the same wave eqn.




For the future convenience, let's consider a flexible string between two fixed pts $x=0$ & $x=1$.

Assume that the string is perfectly flexible, i.e., only tensile forces can be transmitted along the tangential direction.

⇒ The tension acts with the same magnitude at any part of the string along the tan. dir.

ZOOM UP



The total external forces exerted upon the element Δs (u-direction) is

$$\tau_{(u)} = \tau (\sin \alpha_2 - \sin \alpha_1)$$

Note that $\sin \alpha_1 = \frac{du(x)}{ds} = \frac{du}{dx} \frac{dx}{ds} = \frac{du}{dx} \frac{1}{\sqrt{1 + \left(\frac{du}{dx}\right)^2}}$

So far, our argument doesn't include "t". So for the moment, we write $\frac{du}{dx}$ instead of $\frac{\partial u}{\partial x}$.
 as before, $\sqrt{1 + \left(\frac{du}{dx}\right)^2} = 1 + \frac{1}{2} \left(\frac{du}{dx}\right)^2 + O\left(\left(\frac{du}{dx}\right)^4\right)$
negligible

Then $\sin \alpha_1 = \frac{du}{dx} \frac{1}{\sqrt{1 + \left(\frac{du}{dx}\right)^2}} \approx \frac{du}{dx} = u'(x)$

How about $\sin \alpha_2$?

$\sin \alpha_2 = \frac{du}{ds}(x + \Delta x) \approx \frac{du}{dx}(x + \Delta x) \stackrel{\text{Mean Value Thm.}}{=} u'(x) + u''(\xi)\Delta x$
 $\uparrow$
 $ds \approx dx$ $\exists \xi \in [x, x + \Delta x]$

So, $\tau(u) = \tau(\sin \alpha_2 - \sin \alpha_1) \approx \tau u''(\xi)\Delta x$
 $= \tau u_{xx}(\xi)\Delta x$ — ①

Now, the inertial force exerted by the same element Δs is $\rho \Delta s u_{tt} = \text{mass} \times \text{acceleration}$ — ②

By equating ① & ② and dividing by Δx , we have

$$\rho \frac{\Delta s}{\Delta x} u_{tt} = \tau u_{xx}(\xi)$$

Taking the limit $\Delta x \rightarrow 0$, we have $\xi \rightarrow x$, $\frac{\Delta s}{\Delta x} \rightarrow \frac{ds}{dx} \approx 1$
 assuming $\frac{\partial u}{\partial x}$: small.

$\Rightarrow (*) \quad \rho u_{tt} = \tau u_{xx}$ or

$$u_{tt} = \frac{\tau}{\rho} u_{xx} = c^2 u_{xx}, \quad c = \sqrt{\frac{\tau}{\rho}}$$

1D wave eqn. again! velocity

If $\exists$ external force of density $f(x, t)$ acts on the unit length of the string, then

$$\tau(u) \approx \tau u_{xx}(\xi)\Delta s + f(x, t)\Delta s.$$

So, (*) becomes

$$(**) \quad u_{tt} = \frac{\tau}{\rho} u_{xx} + \frac{1}{\rho} f(x, t)$$

Similarly, if we want to use Hamilton's principle then the action becomes

$$\frac{1}{2} \int_{t_1}^{t_2} \int_0^1 [\rho u_t^2 - \tau u_x^2 + 2fu] dx dt \rightarrow \min!$$

i.e., $V = \frac{1}{2} \int_0^1 \tau u_x^2 dx - \underbrace{\int_0^1 f(x,t) u(x,t) dx}_{= \text{Work}}$

$\Rightarrow$ The E-L eqn. leads to (**) again!

★ Toward a solution of the string (1D Wave) eqn.
— Separation of variables + Superposition Principle

$$u_{tt} = c^2 u_{xx}, \quad c^2 = \frac{\tau}{\rho}$$

Do the coordinate transf. via $\sqrt{\tau} t \rightarrow \text{new } t$
 $\sqrt{\rho} x \rightarrow \text{new } x$

to get $u_{tt} = u_{xx}$ (*)

Let's consider this string eqn. on $[0, \pi]$ with
 { B.C. (Dirichlet) $u(0,t) = u(\pi,t) = 0, \forall t$
 { I.C. $\begin{cases} u(x,0) = \phi(x) \in C_0^1[0,\pi], \text{ i.e., } \phi \in C^1[0,\pi] \\ u_t(x,0) = 0 \end{cases}$ & $\phi(0) = \phi(\pi) = 0$

Let's reduce this PDE to a set of ODEs since the latter are easier to solve!

Assume the solution can be written in the form

$$\underline{u(x,t) = X(x) \cdot T(t)} \quad (**)$$

Separation of variables

aka Daniel Bernoulli's separation method

Now, the B.C. above leads to $X(0) = X(\pi) = 0$
 whereas the 0 velocity I.C. " " $T'(0) = 0$

Let's plug (**) into (*):

$$(X \cdot T)_{tt} = X \cdot T'' = (X \cdot T)_{xx} = X'' \cdot T$$

For a region of (x, t) where $u(x, t) \neq 0$,
divide the above by $u = X \cdot T$ to get

$$\frac{\underbrace{T''(t)}_{\text{a fn of } t}}{\underbrace{T(t)}} = \frac{\underbrace{X''(x)}_{\text{a fn of } x}}{\underbrace{X(x)}} = \text{must be a const.} =: \lambda$$

$$\Leftrightarrow \begin{cases} X'' - \lambda X = 0 & \text{--- ① B.C. } X(0) = X(\pi) = 0 \\ T'' - \lambda T = 0 & \text{--- ② I.C. } T'(0) = 0. \end{cases}$$

①: The general sol. $X(x) = a_1 e^{\sqrt{\lambda}x} + a_2 e^{-\sqrt{\lambda}x}$
The characteristic eqn $a_1, a_2 \in \mathbb{R}$

$$r^2 - \lambda = 0 \Rightarrow r = \pm \sqrt{\lambda}.$$

Case I: $\lambda > 0$. Then $\pm \sqrt{\lambda} \in \mathbb{R}$

$$\text{So, } X(0) = a_1 + a_2 = 0 \Leftrightarrow a_2 = -a_1$$

$$X(\pi) = a_1 e^{\sqrt{\lambda}\pi} + a_2 e^{-\sqrt{\lambda}\pi} \\ = a_1 (e^{\sqrt{\lambda}\pi} - e^{-\sqrt{\lambda}\pi}) = 0$$

$$\Leftrightarrow a_1 = 0 = a_2 \#$$

Case II: $\lambda = 0$. Then $X'' = 0$, so $X(x) = a_1 + a_2 x$.

$$X(0) = a_1 = 0, \quad X(\pi) = a_2 \pi = 0 \Leftrightarrow a_2 = 0 \#$$

Case III: $\lambda < 0$. Let's set $\lambda = -\mu^2$, $\mu \in \mathbb{R}$

Then we get $X(x) = a_1 \cos \mu x + b_1 \sin \mu x$
 $\exists a_1, b_1 \in \mathbb{R}.$

$$X(0) = a_1 = 0, \quad X(\pi) = b_1 \sin \mu \pi = 0.$$

Since $b_1 \neq 0$, we have $\sin \mu \pi = 0$.

i.e., $\mu \in \mathbb{Z} \setminus \{0\}$. But the negative sign can be absorbed in the arbitrariness of b_1 ,

So, it suffices to consider $\mu = k \in \mathbb{N}$.

i.e., $\mu = 1, 2, \dots$

$$\Rightarrow X(x) = b_1 \sin kx \quad \text{--- ①'} \quad b_1 \in \mathbb{R}$$

$$\textcircled{2}: T'' - \lambda T = 0 \Rightarrow T' + k^2 T = 0, \quad k \in \mathbb{N}.$$

$$\text{So, } T(t) = a_2 \cos kt + b_2 \sin kt$$

$$T'(t) = -a_2 k \sin kt + b_2 k \cos kt$$

$$T'(0) = b_2 k = 0 \iff b_2 = 0.$$

$$\Rightarrow T(t) = a_2 \cos kt \quad \text{--- ②'} \quad a_2 \in \mathbb{R}$$

From ①' & ②', we see $u_k(x, t) = b_k \sin kx \cos kt$
 $b_k \in \mathbb{R}$ for each $k \in \mathbb{N}$ is a sol. to the string eqn. with those B.C. and I.C. (velocity I.C.)

The remaining problem: how to satisfy the other half of I.C., i.e., $u(x, 0) = \phi(x)$?

But, the only constraint is $\phi \in C_0'[0, \pi]$.

We can **not** assume $\phi(x) = C \cdot \sin kx$, $C \in \mathbb{R}$.

The idea: Since $u_{tt} = u_{xx}$ is **linear**,
 if $\phi(x) \approx \sum_{k=1}^n b_k \sin kx$ (i.e., a trig. poly.)
 then $u(x, t) \approx \sum_{k=1}^n b_k \sin kx \cos kt$.

Since $k = 1, 2, \dots, n, n+1, \dots$, why not
 consider $\sum_{k=1}^{\infty} b_k \sin kx \rightarrow$ **Fourier (sine) series**

Many questions naturally arise:

- For a given $\phi(x) \in C_0'[0, \pi]$, how to compute $\{b_k\}$?
- How fast does b_k decay? (faster decay $\rightarrow$ better approx.)
- What is the mode of convergence?
 uniform? pointwise? norm?
- Can we weaken the condition on $\phi \in C_0'[0, \pi]$?
 say, $\phi \in C_0[0, \pi]$?
- Can we get faster decay if $\phi \in C_0^m[0, \pi]$, $m > 1$?

These will be addressed later when we discuss **Fourier Series**!

Remark: $\exists$ linear PDEs where the sep. of var's does not work. See, e.g., an article by V.G. Papanicolaou in the ref. page.

Remark on B.C./I.C. in general

- For ODEs, e.g., $y^{(n)} = f(x, y, y', \dots, y^{(n-1)})$ of order n , a **general sol.** contains n arbitrary const's. e.g., $y = y(x, c_1, \dots, c_n)$
 $\Rightarrow$ To resolve $c_1, \dots, c_n$, we need n constraints often in the form of B.C.'s and/or I.C.'s, e.g., $y(x_0) = y_0, y'(x_0) = y_1, \dots, y^{(n-1)}(x_0) = y_{n-1}$
- In the case of PDEs, instead of const's, we get arbitrary fcn's!
e.g., $u_{tt} = c^2 u_{xx}$
 $\Rightarrow$ a **general sol.** is

$$u(x, t) = f(x - ct) + g(x + ct)$$

where f, g are **arbitrary C^2 fcn's**.

$\Rightarrow$ To get a sol. describing a specific process/phenomenon, we need rather severe B.C.'s and/or I.C.'s, i.e., those involving **fcn's**!